


How to Define the TBMGR_CEL_LIB variable in MicroStation

1. Load MicroStation and open any design file.
2. Select *Workspace | Configuration...* and MicroStation's Configuration dialog box will open.



From MicroStation's Configuration dialog box you can edit, define, save, and delete variables which can significantly enhance your design environment.

3. Press the {New...} button.
4. In the "Variable:" field enter:
TBMGR_CEL_LIB
5. In the "New Value:" field enter the full path and file name for the cell library you want to use.
6. Press {OK} to exit this dialog box and then {OK} on the Configuration dialog box. You will be prompted with an Alert dialog box to "Save changes to your configuration file." Press {Yes} to accept the changes.
7. You must restart MicroStation for the changes to take effect.